



Leveling/Toe feet - User Guide

1. Using the attributes

1. Select a cabinet in any ortho view
2. Set the attribute filter to "**Toe**" to have the option to apply cabinet feet
3. Selecting the attribute "**All Toe Parts**" will apply feet on the Toe kick sides. "**Side and Toe Parts**" attribute will apply feet on the ends of the cabinet.
4. Once the option chosen, an other attribute will allow you to select the foot type.
5. By clicking on the toe kick parts or on the ends of the cabinet, some attributes of quantities, rotation and position adjustment will appear.





2. Settings

There are two settings on this package:

2.1. Language

i When you click on a cabinet, the attributes will be in the language of your choice: English or French.

If you wish to change this option:

1. Go to the User Created Standards list
2. Click on the UCS called **PV-1.0-Pied verin__Toe Feet**
3. In the public variables, select the Language you wish

2.2. Modify the feet operations

1. Go to the model on the foot from the **"Material Manager"**
2. With the CAM of the model editor, add or modify the operations

